

24 HOURS TO KEYBOARD MASTERY

TOUCH 'n' GO

FOR THE PCW 8256, 8512, 9512, 9256 & 9512+



Harcourt Systems

TOUCH 'n' GO FOR THE PCW

24 hours to keyboard mastery

What is Touch 'n' Go



Having spent a small fortune on your latest bit of software, hovering over the keys looking for the letter 'E' seems a bit silly! This is where Touch 'n' Go comes in.

Touch 'n' Go is a carefully designed keyboard skills course, consisting of a series of lessons, which has been developed over the past 20 years. By working through each of the lessons you will gradually improve your typing skills.

Touch 'n' Go displays all your mistakes and also the speed and accuracy with which you complete each lesson.

Making a working copy

It is important to make a working copy of the masterdisk in case of damage that may be caused when using the program. Once a working copy has been made the master disk should be stored in a safe place.

To make a working copy for your machine follow the procedure which applies to your PCW

For the PCW 8256 or the PCW 8512 (3" Disk)

1. Insert side 2 (CP/M+) of your original system disks in drive A:
2. Reset the computer by pressing SHIFT, EXTRA & EXIT simultaneously. This will load the CPM+ operating system

3. This will display an A> prompt. At this prompt type in DISCKIT and press the enter.
4. Press the F6/F5 key to copy a disk.
5. Follow the on screen prompts to copy a disk.

For the PCW 9256 or the PCW 9512+ (3½" Disk)

1. Insert disk 2 (CP/M+) of your original system disks in drive A:
2. Reset the computer by pressing SHIFT, EXTRA & EXIT simultaneously. This will load the CPM+ operating system
3. This will display an A> prompt. At this prompt type in DISCKIT and press the enter.
4. Press the F6/F5 key to copy a disk.
5. Follow the on screen prompts to copy a disk.

For the Amstrad PCW 9512 (3" Disk)

1. Insert disk 2 (CP/M+) of your original system disks in drive A:
2. Reset the computer by pressing SHIFT, EXTRA & EXIT simultaneously. This will load the CPM+ operating system
3. This will display an A> prompt. At this prompt type in DISCKIT and press the enter.
4. Press the F3/F4 key to Format a disk.
5. Exit Disckit and at the A>, insert the CPM disk.
6. Type 8000COPY and follow the onscreen prompts.
The 'normal capacity' disk is the Touch 'n' Go master disk and the High capacity disk is the formatted disk.

Using Touch 'n' Go

To start Touch 'n' Go insert your CPM+ disk in drive A:, press SHIFT EXTRA & EXIT simultaneously to restart the machine, this will display an A> on your screen, remove the CPM+ disk and insert your working copy of Touch 'n' Go in drive A:.

At the A> type T and press the enter or return key. From here follow the on screen instructions.



Paperback Software Ltd.

Kenwood Nurseries,

Waltham Road,

Boreham,

Chelmsford, Essex.

Tel (0245) 465505 Fax (0245) 465515

© 1987-1993 Paperback Software.